



## DoorVaani.com Asterisk Configuration

Tested on Asterisk Version 13.5.0

To configure Asterisk with a DoorVaani.com VOIP Line as a SIP Trunk for making outgoing calls, a couple of files in the Asterisk configuration directory (/etc/asterisk by default) are to be changed as shown below.

### **File 1: sip.conf**

- i. In the [general] section please add a register statement of the following format using your DoorVaani.com VOIP Line Username and VOIP Line password

register => **voip\_line\_username:voip\_line\_password@as1.doorvaani.com:5060/voip\_line\_username**

- ii. Add a new section at the bottom of the file as follows using your own DoorVaani.com VOIP Line username and VOIP Line password

```
[doorvaani]

type=friend
username=voip_line_username
secret=voip_line_password
context=dv-outgoing
host=as1.doorvaani.com
disallow=all
allow=ulaw
allow=alaw
allow=g729
```

### **File 2: extensions.conf**

In your dialplan locate the line containing the call to the Dial function and ensure that the first parameter of the Dial function is like this: SIP/\${EXTEN}@doorvaani (see below).

exten => **\_1XXXXXXXXXX,n,Dial(SIP/\${EXTEN}@doorvaani, 30)**

Notes:

1. You must reload both sip and dialplan to make the above changes available. Run the following commands to reload SIP and dialplan at the asterisk command line

```
sip reload
```

```
dialplan reload
```

2. Run the following command as the asterisk command line to see your line registered

```
sip show registry
```