

1. On a new install of Zoiper or when no accounts are configured, when you open Zoiper you will directly see the "Add Account" screen. Click "Add account".



2. Please choose Account Type: Click on "SIP" to select "SIP" type of account.



3. SIP Account details screen will open.

L III		78%	9:22	РМ
SIP Account				
Account name				
Authentication				
Host				
Username				
Password				
Optional				
Authentication us	er			
Outbound proxy				
Save		Са	ncel	

4. Touch on AccountName and enter any account name you want. For example: DoorVaani and then click "OK".

	∎ 78% <mark>–</mark> 9:23 PM
SIP Account	
Account name	
Host	
Account name	
DoorVaani	
ок	Cancel
Authentication us	er
Outbound proxy	
Save	Cancel

5. In the Authentication section of SIP Account screen you will see three items: Host, Username and password. Click on "Host" and enter host as "as1.doorvaani.com" and click "OK".

L III	🚺 🔏 78% 🛑 9:24 PM
SIP Account	
Account name DoorVaani	
Authentication	
Host	
Host	
gUsername	
as1.doorvaani.com	n l
Password	
ок	Cancel
Authentication us	ser
Outbound proxy	
Save	Cancel

6. Click on "Username" item in the SIP Account screen. Here you will be entering your "VOIP Line" username you created in your DoorVaani.com account. If you don't have VOIP Line username please login into your DoorVaani.com account

and create one for yourself. DoorVaani.com offers FREE account registration and FREE VOIP Line creation.

	Î	78%	9:25 PM
Account nam	e		
Host as1.doorvaani.com Username			
MyVOIPLine			
ОК		Ca	ncel
Authenticatio	n use	27	
Outbound pro	ху		
Save		Ca	ancel

7. Click on "password" item on SIP Account screen and enter the password associated with your VOIP Line Username you entered in the above step. Please recall that you entered a password when you created your VOIP Line username in your DoorVaani.com. Just in case you don't know the password, you can reset it in your DoorVaani.com account.

	🗊 🔟 78% 🛑 9:26 PM
Account name	e
Host as1.doorvaani.com Password	
ОК	Cancel
Authentication	n user
Outbound pro	xy
Save	Capaci

8. Now scroll to the bottom of SIP Account screen and you will see "Network Settings" item. Click on Network Settings.

	î 🗋	77%	9:32	ΡM
letwork Settings				
Registratior	ı expir	y time		
Transport ty	/pe			
NAT				
Use STUN				
STUN Serve				
STUN Port 3478				
STUN Refre	sh per	iod (m	s)	
Use RPORT	for sig	gnallin	g	

9. Click on "Use STUN" and select "Use default" as shown in the screen below:

	🗊 🚹 🔏 77% 🛑 9	:33 PM
Registration	n expiry time	
Use STUN		
No		
Use default		
Use custom		
	Cancel	
30000		
Use RPORT	for signalling	

10. Tap the back button of your phone and save the settings. You should see the registering screen. On successful registration you can dial numbers.



11. Screen shot when the account is ready to make and receive calls

